

Appendix B - Camera Reader Defaults - iOS (v2.1.x)

Appendix B - Camera Reader Defaults - iOS

The following table lists the defaults the SDK uses on startup for the camera reader.

Note: At the low-level, the cmbSDK supported devices can perform two types of configuration resets: a device reset and a config reset. A device reset restores all configuration properties to their saved defaults, while a config reset restores mostly the scanning settings, leaving communication settings alone. In the table below, those items that are only reset by a device reset are indicated.

Note: The Reader Device method [resetConfig\(\)](#) performs a config reset. To perform a device reset, the [DMCC](#) command [DEVICE.DEFAULT](#) would need to be issued.

SETTING	DEFAULT VALUE	DEVICE RESET ONLY?
BEEP.GOOD	1 1 (Turn beep on)	
C11.CHKCHAR	OFF	
C11.CHKCHAR-OPTION	1	
C39.ASCII	OFF	
C39.CHKCHAR	OFF	
C93.ASCII	OFF	
COM.DMCC-HEADER	1 (Include Result ID)	Y
COM.DMCC-RESPONSE	0 (Extended)	Y
DATA.RESULT-TYPE	1	Y
DECODER.1D-SYMBOLORIENTATION	1	
DECODER.EFFORT	2	

SETTING	DEFAULT VALUE	DEVICE RESET ONLY?
DECODER.MAX-SCAN-TIMEOUT	60	
DEVICE.NAME	"MX-" + the last six digits of DEVICE.SERIAL-NUMBER	
Symbologies (SYMBOL.*)	OFF (all symbologies are disabled)	
Symbology sub-types (groups): DATABAR.EXPANDED DATABAR.LIMITED DATABAR.RSS14 DATABAR.RSS14STACK UPC- EAN.EAN13 UPC-EAN.EAN8 UPC-EAN.UPC-A UPC-EAN.UPC- E UPCE- AN.UPCE1	ON OFF OFF OFF ON ON ON ON OFF	
FOCUS.FOCUSTIME	3	
I2O5.CHKCHAR	OFF	
IMAGE.FORMAT	1 (JPEG)	
IMAGE.QUALITY	50	
IMAGE.SIZE	1 (1/4 size)	
LIGHT.AIMER	Default based on cameraMode: 0: NoAimer and FrontCamera 1: PassiveAimer and ActiveAimer	Y
LIGHT.AIMER-TIMEOUT	60	
LIGHT.INTERNAL-ENABLE	OFF	

Appendix B - Camera Reader Defaults

Setting	Default Value	Device Reset Only?
Minimum/maximum code lengths	ON 4 40	
MSI.CHKCHAR	OFF	

MSI.CHKCHAR-OPTION

0

TRIGGER.TYPE

2 (Manual)

UPC-EAN.SUPPLEMENT

0